



Outlook Express IMAP 設定方式

1.開啟 Outlook Express →工具→選擇「帳戶」→選擇「新增」→郵件，輸入欲顯示的名稱。




The screenshot shows the 'Internet Connection Wizard' dialog box with the title '網際網路連線精靈'. The current step is '您的名稱' (Your Name). The text below the title reads: '傳送電子郵件時，您的名稱會出現在外送郵件的 [寄件者] 欄位。請輸入您希望出現的名稱。' (When sending email, your name will appear in the [Sender] field of outgoing mail. Please enter the name you want to appear). There is a text input field labeled '顯示名稱 (N):' (Display Name) containing the text 'start'. Below the field is an example: '範例: 祝英台' (Example: Zhu Yingtai). At the bottom, there are three buttons: '< 上一步 (B)' (Previous Step), '下一步 (N) >' (Next Step), and '取消' (Cancel). The 'Next Step' button is highlighted with a red box.

2.輸入電子郵件地址



The screenshot shows the 'Internet Connection Wizard' dialog box with the title '網際網路連線精靈'. The current step is '網際網路電子郵件地址' (Internet Email Address). The text below the title reads: '電子郵件地址是供其他人傳送電子郵件給您。' (Email address is for others to send email to you). There is a text input field labeled '電子郵件地址 (E):' (Email Address) containing the text 'start@ntu.edu.tw'. Below the field is an example: '例如: someone@microsoft.com' (Example: someone@microsoft.com). At the bottom, there are three buttons: '< 上一步 (B)' (Previous Step), '下一步 (N) >' (Next Step), and '取消' (Cancel). The 'Next Step' button is highlighted with a red box.

3.選擇「IMAP」伺服器，內送郵件(POP3、IMAP 或 HTTP)伺服器:
mail.ntu.edu.tw，外送郵件伺服器: mail.ntu.edu.tw。



網際網路連線精靈

電子郵件伺服器名稱

我的內送郵件伺服器是 (S) 伺服器。←選 IMAP


內收郵件 (POP3、IMAP 或 HTTP) 伺服器 (I):
 ←mail.ntu.edu.tw

SMTP 伺服器是處理外送郵件的伺服器。

外寄郵件伺服器 - SMTP (O):
 ←mail.ntu.edu.tw

< 上一步 (B) **下一步 (N) >** 取消

4.輸入您的帳號與密碼，請記得勾選「使用安全密碼驗證(SPA)登入」，點選下一步→點選完成。



網際網路連線精靈

網際網路郵件登入

請建立網際網路服務提供者給您的帳戶名稱及密碼。

帳戶名稱 (A):

密碼 (P):

記憶密碼 (M)


如果您的網際網路服務提供者要求您使用 [安全密碼驗證] (SPA) 來存取您的郵件帳戶，請選擇 [使用安全密碼驗證登入] 選項。

使用安全密碼驗證 (SPA) 登入 (S) ←記得勾選


< 上一步 (B) **下一步 (N) >** 取消




5. 選擇您剛設定的帳戶 → 點選「內容」。



6. 點選「伺服器」 → 請記得勾選「使用安全密碼驗證登入」、「我的伺服器需要驗證」。



7.點選「進階」→勾選「這個伺服器需要安全連線 SSL」，外寄郵件-SMTP: 587，
內送郵件-IMAP: 993→點選「確定」。



先勾選這個伺服器需要安全連線(SSL)，

內送郵件(IMAP): 993

外寄郵件(SMTP): 587